

Version 5 Software Update

Visual C||Cure

Visual Studio 2026

The entire code base is now compiled using Visual Studio 2026, ensuring up-to-date compilers and debugging tools are being used to help reduce bugs.



Native Unicode support

Previous versions of Visual C||Cure have been written using a custom implementation of Unicode support. The code base has now been updated to use native Unicode data types whilst still maintaining UTF8 support as used on the target devices.



Better support for multiple monitors

Multiple monitor development setups are now more common than ever. Due to this, better support has been added to maintain dialog and window positions across any connected monitor.

Enhanced language support

Language support has been greatly enhanced to allow the user to fully translate all aspects of the application when viewed via the internal website.

Previously, only database pins supported alternative Unicode language translation strings. Language support has been extended to include Display Menus (as used on, for example, the internal website) and Tables (which previously only supported a single “alias” alternative).

The Table manager has been rewritten to allow each table entry to have its own translation per configured language.

A diagram illustrating the evolution of the Table manager. On the left, labeled 'Old Table Manager', is a screenshot of a table with two columns: 'Value' and 'Text'. The data rows are '0 NO' and '1 YES'. To the right, labeled 'New Table Manager', is a screenshot of a table with six columns: 'Entry', 'Name', 'English', 'Français', 'Deutsch', and 'Español'. The data rows are '0 NO No Non Nein No' and '1 YES Yes Oui Ja Sí'. A large blue arrow points from the 'Old Table Manager' screenshot to the 'New Table Manager' screenshot.

Value	Text
0	NO
1	YES

Entry	Name	English	Français	Deutsch	Español
0	NO	No	Non	Nein	No
1	YES	Yes	Oui	Ja	Sí


Furthermore an additional table, called SYSLANG, has also been added which contains over 400 entries for all the system strings used on the target website. See the website section below for an example.

New predefined units table

In order to standardize across library blocks, new applications will now have an extensive UNITS table containing a predefined set of units, split into groups such as distance, time, weight and volume.

	Entry	Name	English	Français	Deutsch	Español
SYSINFO	6003	cubic kilometres	km ³			
SYSINFO2	6004	litres	l			
SYSLANG	6005	fl oz (US)	fl oz			
UNITS	6006	Cubic Inch	in ³			
USERS	6007	Cubic Foot	CF			
ZONES	6008	100 CF	CCF			

If a custom set or a subset of units is required, the “Add New Table” dialog has been redesigned to allow existing table entries to be copied selectively into the new table.



NANOConf

Granular install options


When installing an application onto a target device, the user now has greater control over what settings and features should (or shouldn't) be updated.

The user can now choose between the following Install Types:

New Install Any settings contained within the application file are used.

Upgrade The target device retains its existing settings.

Custom For each setting, the user can choose to keep the existing setting, use the new application setting or reset to factory default.



Note that to retain backward compatibility, if the target unit is still running v4 of the firmware, all options are preset so it emulates the previous method of installation.

Synchronized column widths

As a simple quality-of-life enhancement, the column widths of the “stored” and “local” device lists are now synchronized.

Column widths are also now saved on close and restored on startup.

NANO Target Firmware

Dynamic language support

To complement the additional language support as mentioned in the Visual C||Cure section above, the website has been updated to allow the same enhanced language support.

When multiple languages are defined in an application, a new language icon is displayed in the top right corner of the website.

The screenshot shows a web-based interface for the NANO Target Firmware. At the top, there's a navigation bar with tabs for Home, System Logs, Event Logs, and System Event Log. On the far right of the header, there's a timestamp (2026/01/06 12:44:26) and a small globe icon. Below the header is a horizontal menu with icons for Home, System Logs, Event Logs, and System Event Log. The main content area displays a three-month calendar for 2026 (January, February, March). Each month grid shows days of the week from Sunday to Saturday, with specific dates highlighted in blue. A mouse cursor is hovering over the globe icon in the header, which triggers a dropdown menu listing available languages: English, Français, Deutsch, and Español. The English option is currently selected.

Hovering over this brings up a list of available languages.

This screenshot is similar to the previous one but focuses on the language selection dropdown. The dropdown menu is open, showing four options: English, Français, Deutsch, and Español. The English option is highlighted with a blue circle and a checkmark. The other three options are in a smaller, standard font. The rest of the page, including the calendar, remains visible in the background.

Selecting one of the languages causes the website to dynamically refresh any pin names, table entries and system text using any available translation strings.

This screenshot shows the website after the French language has been selected. The language dropdown menu is still open, but the French option is now highlighted with a blue circle and a checkmark. The rest of the page, including the calendar, has been refreshed to reflect the French language settings. The text in the header and the calendar grid is now in French.

Support Tunneling

A new “support tunneling” feature has been added which can be enabled to allow the factory to provide remote support. Although disabled by default, when enabled (via the internal website) it turns on a “contact the factory” message every 10 minutes. The factory is then able to connect remotely in order to backup and install updates to the unit.

The advantage of this feature is that, since the remote device is instigating the connection, it allows support without the need to modify the user’s firewall to enable remote access.

Configurable DNS entries

Full control over the DNS table for the primary network port has been added to the Network page on the internal website.

If in DHCP mode, the current DNS entries are displayed (read-only).

If in Static mode, two DNS entries can be manually configured to suit the user’s network requirements.